

cambri●nix

LiveViewer User Guide - Mac





Contents

1 - Downloading and Installing LiveViewer 3

2 - Using LiveViewer 3

3 - Keyboard shortcuts 4




1 - Downloading and Installing LiveViewer

1) Open your preferred web browser and go to <http://www.cambriONIX.com/downloads/liveviewer/>

2) Select the link for Mac, a zip folder will download.



3) Open the folder from the usual download place and open the .dmg file.



4) A shortcut for LiveViewer can be created in the usual way.




2 - Using LiveViewer

1) Launch the application in the usual way.

2) Connect the desired product to the host computer via its update and control port.

3) Click 'Scan' to find the connected products and select the product by clicking on it and clicking the 'LiveView' Button or by double clicking the product.





4) A table will now be displayed with up to date real time information about the connected devices.

Port	Status	Mode	Profile	Duration	End time	Current	Energy
1	<input checked="" type="checkbox"/>	sync					
2	<input checked="" type="checkbox"/>	attached	sync			1434mA	
3	<input checked="" type="checkbox"/>	sync					
4	<input checked="" type="checkbox"/>	sync					
5	<input checked="" type="checkbox"/>	sync					
6	<input checked="" type="checkbox"/>	attached	sync			1434mA	
7	<input checked="" type="checkbox"/>	attached	sync			68mA	
8	<input checked="" type="checkbox"/>	sync					
9	<input checked="" type="checkbox"/>	sync					
10	<input checked="" type="checkbox"/>	sync					
11	<input checked="" type="checkbox"/>	attached	sync			1424mA	
12	<input checked="" type="checkbox"/>	sync					
13	<input checked="" type="checkbox"/>	sync					
14	<input checked="" type="checkbox"/>	sync					
15	<input checked="" type="checkbox"/>	attached	sync			1415mA	

5) To select a port simply tick the box next to it. Tick the box above all the ports to select all ports.

Port	Status	Mode	Profile	Duration	End time	Current	Energy
1	<input type="checkbox"/>	idle					
2	<input type="checkbox"/>	attached	charging	profile 1	27m50s	1981mA	4.59 Wh
3	<input type="checkbox"/>	idle					
4	<input type="checkbox"/>	idle					
5	<input type="checkbox"/>	idle					
6	<input type="checkbox"/>	attached	charging	profile 1	27m50s	2020mA	4.66 Wh
7	<input checked="" type="checkbox"/>	attached	profiling	profile 2		87mA	
8	<input type="checkbox"/>	idle					
9	<input type="checkbox"/>	idle					
10	<input type="checkbox"/>	idle					
11	<input type="checkbox"/>	attached	charging	profile 1	27m50s	2010mA	4.63 Wh
12	<input type="checkbox"/>	idle					
13	<input type="checkbox"/>	idle					
14	<input type="checkbox"/>	idle					
15	<input type="checkbox"/>	attached	charging	profile 1	27m49s	2010mA	4.61 Wh

6) Once the ports have been selected the port function can be changed to either 'Off', 'Sync' or 'Charge' mode. This can also be done by double finger clicking on the port's row.

Charge Mode - Charges the connected devices at the manufactures optimum rate

Sync Mode - Connects the devices to the host computer as if they were connected directly.

Off Mode - Turns the ports off, providing no current to the connected devices.

3 - Keyboard shortcuts

C	Switch selected ports to charge mode
S	Switch selected ports to sync mode
O	Switch off selected ports
/	Select all ports
Number Keys	Select that numbered port
*	Switch selected ports to sync mode
-	Switch off selected ports
+	Switch selected ports to charge mode